



AstroLib Coords Documentation

Release 0.39 (2009-01-06)

Vicki Laidler

April 18, 2016

CONTENTS

1	README	3
1.1	Purpose	3
1.2	Dependencies	3
1.3	Examples	3
1.4	TPM Citation	5
1.5	See Also	5
2	coords.position.Position	7
2.1	Utility Functions	9
3	coords.position.Coord	11
3.1	Subclasses	11
4	coords.angsep	13
5	coords.astrodate	15
5.1	Global Variables	17
6	coords.pytpm_wrapper	19
6.1	Global Variables	19
7	Indices and tables	23
	Python Module Index	25
	Index	27

Contents:

1.1 Purpose

This package aims to provide much of the IDL “astron” functionality that pertains to coordinate manipulations in an OO framework. Our target user is a typical astronomer who needs to analyze data, work with catalogs, prepare observing proposals, and prepare for observing runs.

The initial version will provide simple functionality for working with positions in the same reference frame, without having to worry about units.

1.2 Dependencies

numpy

pytpm – a Python wrapper for the TPM library graciously contributed by Jeff Percival

1.3 Examples

```
>>> import astrolib.coords as C
>>> print C.__version__
0.39
```

Unit conversions

```
>>> ob = C.Position('12:34:45.34 -23:42:32.6')
>>> ob.hmsdms()
'12:34:45.340 -23:42:32.600'
>>> ob.dd()
(188.68891666666667, -23.709055555555555)
>>> ob.rad()
(3.2932428578545374, -0.41380108198269777)
```

Angular separations

```
>>> p1 = C.Position("01:23:45.300 +65:43:31.240")
>>> p2 = C.Position("01:23:45.62 +65:43:31.20")
>>> p1.angsep(p2)
0.000548 degrees
>>> delta = p1.angsep(p2)
>>> delta.arcsec()
1.973739377865491
```

```
>>> p1.within(p2, 3.0, units='arcsec')
True
>>> epsilon = C.AngSep(5.0)
>>> epsilon
5.000000 arcsec
>>> delta > epsilon
False
```

Astronomical Date specifications

```
>>> d = C.AstroDate('1997.3') # Defaults to Julian year; J or B prefix also ok
>>> d.year
1997.3
>>> d.jd
2450558.8250000002
>>> d.mjd
50558.325000000186
>>> d2 = C.AstroDate('MJD50658.25') # JD also ok for plain Julian Date
>>> d2.year
1997.5735797399041
>>> d2 < d
False
```

Coordinate conversions

```
>>> ob.j2000()
(188.68891666666667, -23.709055555555555)
>>> ob.b1950()
(188.03056480942405, -23.433637283819877)
>>> ob.galactic()
(298.01638938748795, 39.003358150874568)
>>> ob.ecliptic(timetag=C.AstroDate('J2000'))
(197.5848634558852, -18.293964120804738)
>>> p3 = C.Position("01:23:45 -65:43:21.4", equinox='J2000')
>>> p4 = C.Position("01:23:45 -65:43:21.4", equinox='B1950')
>>> p3.j2000()
(20.9375, -65.722611111111107)
>>> p4.j2000()
(21.356870704681981, -65.462921080444147)
>>> p3.angsep(p4)
0.312199 degrees
>>> p5 = C.Position((0.0,0.0), system='galactic')
>>> p5.j2000()
(266.40499571858879, -28.936169261309555)
```

Specify position in hmsdms

```
>>> polaris = C.Position("02:31:49.08 +89:15:50.8")
>>> polaris.dd()
(37.954500000000003, 89.264111111111106)
>>> polaris.hmsdms()
'02:31:49.080 +89:15:50.800'
>>> print polaris.details()
System: celestial
Equinox: j2000
```

Specify position in decimal degrees


```
>>> ob = C.Position((52.9860209, -27.7510006))
>>> ob.hmsdms()
'03:31:56.645 -27:45:03.602'
>>> ob.dd()
(52.9860209, -27.751000600000001)
```

Use as calculator without saving the intermediate object

```
>>> C.Position("12:34:45.4 -22:21:45.4").dd()
(188.68916666666667, -22.362611111111111)
```

1.4 TPM Citation

Investigators using this software for their research are requested to explicitly acknowledge “use of the TPM software library, by Jeffrey W. Percival” in any appropriate publications.

1.5 See Also

<http://www.scipy.org/AstroLibCoordsHome>

COORDS.POSITION.POSITION

Position object to manage coordinate transformations.

```
class astrolib.coords.position.Position (input, equinox='J2000', system='celestial',  
                                         units='degrees')
```

The basic class in the coords library. The Position class is designed to permit users to define a position and then access many representations of it.

Attributes

input	The input used to create the Position.
units	({'degrees', 'radians'}) Unit in which the coords were specified.
equinox	(string) Equinox at which the coordinates were specified.
system	({'celestial', 'galactic', 'ecliptic'})
_tpmstate	(integer) The TPM state of the position.
coord	(<i>Coord</i>) A “smart” representation of the position.
_internal	((float, float)) The internal representation of the position (decimal degrees).

Parameters**input** : string (hh:mm:ss.ss +dd:mm:ss.sss) or tuple of numbers (dd.ddd, dd.ddd)

Coordinates of the position.

equinox : string

Equinox in which the coords are specified.

system : string

celestial, galactic, ecliptic, etc

units : {'degrees', 'radians'}

angsep (*other*)

Computes the angular separation (great circle distance) between two Positions.

Parameters**other** : another *Position*

Returns**ans** : *AngSep*

Angular separation.

b1950 (*timetag=None*)

Return the position in Mean FK4 B1950 coordinates.

Parameter**timetag** : *AstroDate*

Timetag of returned coordinate.

Returnsr, d : (float, float)

Tuple of RA and DEC in decimal degrees.

dd ()

Returns_internal : (float, float)

Position in decimal degrees.

details ()

Returnsans : string

Formatted `system` and `equinox` for printing.

ecliptic (*timetag=None*)

Return the position in IAU 1980 Ecliptic coordinates.

Parameterstimetag : *AstroDate*

Timetag of returned coordinate.

Returnsr, d : (float, float)

Tuple of (l,e) in decimal degrees.

galactic (*timetag=None*)

Return the position in IAU 1958 Galactic coordinates.

Parameterstimetag : *AstroDate*

Timetag of returned coordinate.

Returnsl, b : (float, float)

Tuple in decimal degrees.

hmsdms ()

Returnsvalue : string

Position in hms dms.

j2000 (*timetag=None*)

Return the position in Mean FK5 J2000 coordinates.

Parameterstimetag : *AstroDate*

Timetag of returned coordinate.

Returnsr, d : (float, float)

Tuple of RA and DEC in decimal degrees.

rad ()

Returnsr1, r2 : (float, float)

Position in radians.

tpmstate (*endstate, epoch=None, equinox=None, timetag=None*)

This method allows the expert user to call the blackbox routine of the TPM library directly, for access to more state transitions than are supported in this interface. Little documentation is provided here because it is assumed you know what you are doing if you need this routine.

Parametersendstate : integer

As defined by the TPM state machine.

epoch : float

Epoch in Julian date; default is J2000.

equinox : float

Equinox in Julian date; default is `_tpmequinox`.

timetag : *AstroDate*

Timetag of returned coordinate.

Returns`x2, y2` : (float, float)

Transformed coordinates in decimal degrees.

within (*other, epsilon, units='arcsec'*)

Check if *other* is within *self*.

Parameters`other` : another *Position*

epsilon : *AngSep* or number

Angular separation.

units : {'arcsec', 'degrees'}

Unit of *epsilon*, if it is specified as a number.

Returns`ans` : boolean

`True` if *other* is within *epsilon* of *self*.

2.1 Utility Functions

`astrolib.coords.position.dms` (*number*)

Convert from decimal to sexagesimal degrees,minutes,seconds.

Parameters`number` : number

Returns`sign, dd, mm, ss` : (string, int, int, float)

Sign, degrees, minutes, and seconds.

`astrolib.coords.position.gcdist` (*vec1, vec2*)

Input (ra,dec) vectors in radians; output great circle distance in radians.

Parameters`vec1, vec2` : number

Position in radians.

Returns`ans` : number

Great circle distance in radians.

References

<http://wiki.astrogrid.org/bin/view/Astrogrid/CelestialCoordinates>

`astrolib.coords.position.hav` (*theta*)

haversine function, units = radians. Used in calculation of great circle distance.

Parameter`theta` : number

Angle in radians.

Returnsans : number

`astrolib.coords.position.ahav(x)`

archaversine function, units = radians. Used in calculation of great circle distance.

Parametersx : number

Returnsans : number

Angle in radians.

COORDS.POSITION.COORD

class `astrolib.coords.position.Coord`
General class for subclasses.

A `Coord` is distinct from a `Position` by being intrinsically expressed in a particular set of units.

Each `Coord` subclass knows how to parse its own input, and convert itself into the internal representation (decimal degrees) used by the package.

3.1 Subclasses

class `astrolib.coords.position.Degrees` (*input*)
Decimal degrees coord.

Attributes

<code>a1, a2</code>	(float) Longitude and latitude in decimal degrees.
---------------------	--

Parametersinput : (float, float)

Coordinates in decimal degrees.

class `astrolib.coords.position.Hmsdms` (*input*)
Sexagesimal coord: longitude in hours of time (enforced).

Attributes

<code>a1, a2</code>	(Numpy[int,int,float]) Longitude and latitude in hours, minutes, seconds
---------------------	--

Parametersinput : string

Coordinates as hh:mm:ss.sss +dd:mm:ss.sss (sign optional).

class `astrolib.coords.position.Radians` (*input*)
Radians coord.

Attributes

a1, a2	(float) Longitude and latitude in radians.
--------	--

Parametersinput : (float, float)

Coordinates in radians.

COORDS.ANGSEP

Angular separation between two *Position*.

Can be defined by hand, or produced by “subtracting” two positions. Like *Position*, it will have an internal representation, and a variety of user-selected representations.

class `astrolib.coords.angsep.AngSep` (*value*, *units*='arcsec')

The `AngSep` class lets the user compare the angular separation between different *Position* without having to think too much about units.

Each `AngSep` object is created with a particular length in a particular set of units. These are then converted into an internal representation which is used for all math and comparisons.

All unit checks are performed by checking the first few letters of the unit string, to provide more flexibility for the user. E.g., “arc”, “arcs”, “arcsec”, and “arcseconds” will all evaluate to arcseconds.

All math and comparisons can be done either between two `AngSep` objects, or between an `AngSep` object and a number. In the latter case, the number is assumed to have the same units as the `AngSep` object.

Examples

Default units are arcsec

```
>>> a = angsep.AngSep(5)
>>> a
5.000000 arcsec
```

The usual arithmetic works

```
>>> b = angsep.AngSep(3)
>>> a+b
8.000000 arcsec
>>> a*3
15.000000 arcsec
```

Use `AngSep` together with *Position*

```
>>> p1 = P.Position('12:34:45.23 45:43:21.12')
>>> p2 = P.Position('12:34:47.34 45:43:23.0')
>>> sep = p1.angsep(p2)
>>> eps = angsep.AngSep(30,units='arcsec')
>>> p1.within(p2,eps)
True
>>> p2.within(p1,20)
False
```

Note: Angular Separations are inherently positive: negative separations have no physical meaning, and are forbidden.

Attributes

value	(number) Magnitude of the angular separation.
units	(string) Units in which the magnitude is expressed (arcsec, degrees, or radians).
_internal	(number (degrees)) Internal representation of the separation.

Parametersvalue : number

Magnitude of the angular separation.

units : string

Arcsec or degrees.

RaisesValueError

If value < 0. Negative separations are physically meaningless and thus forbidden.

approx (*other*, *epsilon*)

True if self and other are equal to within epsilon, which is considered to have the same units as self.

Note: This is not implemented as 'abs(self-other)<epsilon' because of the prohibition on negative separations.

Parametersother, epsilon : *AngSep* or number (units of self)

Returnsans : boolean

arcsec ()

Returnsvalue : float

Separation in arcsec.

degrees ()

Returnsvalue : float

Separation in degrees.

radians ()

Returnsvalue : float

Separation in radians.

setunits (*units*)

Sets the units of the public representation, and converts the publically visible value to those units

Parametersunits : {'radians', 'arcsec', 'degrees'}

COORDS.ASTRODATE

`class astrolib.coords.astrodate.BesselDate (datespec)`

Attributes

year	(float) Decimal Besselian year
jd	(float) Julian date
mjd	(float) Modified Julian Date
datespec	Date specification as entered by the user

`jyear ()`

Return the julian year using the already-converted julian date.

Returnsans : float

Decimal Julian year

`class astrolib.coords.astrodate.JulianDate (datespec)`

Attributes

year	(float) Decimal Julian year.
jd	(float) Julian date.
mjd	(float) Modified Julian Date
datespec	Date specification as entered by the user

`byear ()`

Return Besselian year based on previously calculated julian date.

Returnsans : float

Decimal Besselian year.

`astrolib.coords.astrodate.AstroDate (datespec=None)`

AstroDate can be used as a class for managing astronomical date specifications (despite the fact that it was implemented as a factory function) that returns either a BesselDate or a JulianDate, depending on the properties of the datespec.

AstroDate was originally conceived as a Helper class for the Position function for use with pytpm functionality, but also as a generally useful class for managing astronomical date specifications.

The philosophy is the same as Position: to enable the user to specify the date once and for all, and access it in a variety of styles.

Todo

1. Add math functions! Addition, subtraction.
 2. Is there a need to support other date specifications? eg FITS-style dates?
-

Parameters`datespec` : string, float, integer, `datetime.datetime`, or `None`

Returns`value` : `JulianDate` or `BesselDate`

Date specification as entered by the user. Permissible specifications include:

• **Julian year**

– ‘J1997’, ‘J1997.325’, 1997.325

– Return a `JulianDate`

• **Besselian year**

– ‘B1950’, ‘B1958.432’

– Return a `BesselDate`

• **Julian date**

– ‘JD2437241.81’, ‘2437241.81’, 2437241.81

– Return a `JulianDate`

• **Modified Julian date**

– ‘MJD37241.31’

– Return a `JulianDate`

• **`datetime.datetime` object**

– Assume input time is UTC

– Return a `JulianDate`

• **`None`**

– Return the current time as a `JulianDate`

Raises`ValueError`

Raises an exception if the date specification is a string, but begins with a letter that is not ‘B’, ‘J’, ‘JD’, or ‘MJD’ (case insensitive).

`astrolib.coords.astrodate.byear2jd` (*byear*)

Parameters`byear` : float

Decimal Besselian year.

Returns`value` : float

Julian date.

`astrolib.coords.astrodate.jd2jyear` (*jd*)

Parameters`jd` : float

Julian date.

Returnsvalue : float

Decimal Julian year.

`astrolib.coords.astrodate.jyear2jd(jyear)`

Parametersjyear : float

Decimal Julian year.

Returnsvalue : float

Julian date.

`astrolib.coords.astrodate.utc2jd(utc)`

Convert UTC to Julian date.

Conversion translated from TPM modules `utcnw.c` and `gcal2j.c`, which notes that the algorithm to convert from a gregorian proleptic calendar date onto a julian day number is taken from The Explanatory Supplement to the Astronomical Almanac (1992), section 12.92, equation 12.92-1, page 604.

Parametersutc : `datetime.datetime` object

UTC (Universal Civil Time).

Returnsvalue : float

Julian date to the nearest second.

5.1 Global Variables

`astrolib.coords.astrodate.B1950 = 2433282.42345905`

`float(x)` -> floating point number

Convert a string or number to a floating point number, if possible.

`astrolib.coords.astrodate.J2000 = 2451545.0`

`float(x)` -> floating point number

Convert a string or number to a floating point number, if possible.

`astrolib.coords.astrodate.CB = 36524.21987817305`

`float(x)` -> floating point number

Convert a string or number to a floating point number, if possible.

`astrolib.coords.astrodate.CJ = 36525.0`

`float(x)` -> floating point number

Convert a string or number to a floating point number, if possible.

`astrolib.coords.astrodate.MJD_0 = 2400000.5`

`float(x)` -> floating point number

Convert a string or number to a floating point number, if possible.

COORDS.PYTPM_WRAPPER

```
astrolib.coords.pytpm_wrapper.blackbox(x, y, instate, outstate, epoch, equinox,  
                                         timetag=None)
```

Parameters**x, y** : float

Position in decimal degrees.

instate, outstate : int

The TPM states of the position.

epoch : float

Epoch of the position.

equinox : float

Equinox of the position.

timetag : *AstroDate*

Timetag of returned coordinate.

Returns**r, d** : float

Converted coordinate.

6.1 Global Variables

```
astrolib.coords.pytpm.b1950 = 2433282.42345905
```

float(x) -> floating point number

Convert a string or number to a floating point number, if possible.

```
astrolib.coords.pytpm.j2000 = 2451545.0
```

float(x) -> floating point number

Convert a string or number to a floating point number, if possible.

```
astrolib.coords.pytpm.CJ = 36525.0
```

float(x) -> floating point number

Convert a string or number to a floating point number, if possible.

```
astrolib.coords.pytpm.CB = 36524.21987817305
```

float(x) -> floating point number

Convert a string or number to a floating point number, if possible.

`astrolib.coords.pytpm.s01 = 1`

`int(x=0) -> int or long int(x, base=10) -> int or long`

Convert a number or string to an integer, or return 0 if no arguments are given. If x is floating point, the conversion truncates towards zero. If x is outside the integer range, the function returns a long instead.

If x is not a number or if base is given, then x must be a string or Unicode object representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>> `int('0b100', base=0) 4`

`astrolib.coords.pytpm.s02 = 2`

`int(x=0) -> int or long int(x, base=10) -> int or long`

Convert a number or string to an integer, or return 0 if no arguments are given. If x is floating point, the conversion truncates towards zero. If x is outside the integer range, the function returns a long instead.

If x is not a number or if base is given, then x must be a string or Unicode object representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>> `int('0b100', base=0) 4`

`astrolib.coords.pytpm.s03 = 3`

`int(x=0) -> int or long int(x, base=10) -> int or long`

Convert a number or string to an integer, or return 0 if no arguments are given. If x is floating point, the conversion truncates towards zero. If x is outside the integer range, the function returns a long instead.

If x is not a number or if base is given, then x must be a string or Unicode object representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>> `int('0b100', base=0) 4`

`astrolib.coords.pytpm.s04 = 4`

`int(x=0) -> int or long int(x, base=10) -> int or long`

Convert a number or string to an integer, or return 0 if no arguments are given. If x is floating point, the conversion truncates towards zero. If x is outside the integer range, the function returns a long instead.

If x is not a number or if base is given, then x must be a string or Unicode object representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>> `int('0b100', base=0) 4`

`astrolib.coords.pytpm.s05 = 5`

`int(x=0) -> int or long int(x, base=10) -> int or long`

Convert a number or string to an integer, or return 0 if no arguments are given. If x is floating point, the conversion truncates towards zero. If x is outside the integer range, the function returns a long instead.

If x is not a number or if base is given, then x must be a string or Unicode object representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>> `int('0b100', base=0) 4`

`astrolib.coords.pytpm.s06 = 6`

`int(x=0) -> int or long int(x, base=10) -> int or long`

Convert a number or string to an integer, or return 0 if no arguments are given. If x is floating point, the conversion truncates towards zero. If x is outside the integer range, the function returns a long instead.

If `x` is not a number or if `base` is given, then `x` must be a string or Unicode object representing an integer literal in the given base. The literal can be preceded by '+' or '-' and be surrounded by whitespace. The base defaults to 10. Valid bases are 0 and 2-36. Base 0 means to interpret the base from the string as an integer literal. >>>
`int('0b100', base=0)` 4

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

a

`astrolib.coords.angsep`, 13
`astrolib.coords.astrodate`, 15
`astrolib.coords.pytpm_wrapper`, 19

A

ahav() (in module astrolib.coords.position), 10
 AngSep (class in astrolib.coords.angsep), 13
 angsep() (astrolib.coords.position.Position method), 7
 approx() (astrolib.coords.angsep.AngSep method), 14
 arcsec() (astrolib.coords.angsep.AngSep method), 14
 AstroDate() (in module astrolib.coords.astrodate), 15
 astrolib.coords.angsep (module), 13
 astrolib.coords.astrodate (module), 15
 astrolib.coords.pytpm_wrapper (module), 19

B

B1950 (in module astrolib.coords.astrodate), 17
 b1950 (in module astrolib.coords.pytpm), 19
 b1950() (astrolib.coords.position.Position method), 7
 BesselDate (class in astrolib.coords.astrodate), 15
 blackbox() (in module astrolib.coords.pytpm_wrapper),
 19
 byear() (astrolib.coords.astrodate.JulianDate method), 15
 byear2jd() (in module astrolib.coords.astrodate), 16

C

CB (in module astrolib.coords.astrodate), 17
 CB (in module astrolib.coords.pytpm), 19
 CJ (in module astrolib.coords.astrodate), 17
 CJ (in module astrolib.coords.pytpm), 19
 Coord (class in astrolib.coords.position), 11

D

dd() (astrolib.coords.position.Position method), 8
 Degrees (class in astrolib.coords.position), 11
 degrees() (astrolib.coords.angsep.AngSep method), 14
 details() (astrolib.coords.position.Position method), 8
 dms() (in module astrolib.coords.position), 9

E

ecliptic() (astrolib.coords.position.Position method), 8

G

galactic() (astrolib.coords.position.Position method), 8
 gcdist() (in module astrolib.coords.position), 9

H

hav() (in module astrolib.coords.position), 9
 Hmsdms (class in astrolib.coords.position), 11
 hmsdms() (astrolib.coords.position.Position method), 8

J

J2000 (in module astrolib.coords.astrodate), 17
 j2000 (in module astrolib.coords.pytpm), 19
 j2000() (astrolib.coords.position.Position method), 8
 jd2jyear() (in module astrolib.coords.astrodate), 16
 JulianDate (class in astrolib.coords.astrodate), 15
 jyear() (astrolib.coords.astrodate.BesselDate method), 15
 jyear2jd() (in module astrolib.coords.astrodate), 17

M

MJD_0 (in module astrolib.coords.astrodate), 17

P

Position (class in astrolib.coords.position), 7

R

rad() (astrolib.coords.position.Position method), 8
 Radians (class in astrolib.coords.position), 11
 radians() (astrolib.coords.angsep.AngSep method), 14

S

s01 (in module astrolib.coords.pytpm), 19
 s02 (in module astrolib.coords.pytpm), 20
 s03 (in module astrolib.coords.pytpm), 20
 s04 (in module astrolib.coords.pytpm), 20
 s05 (in module astrolib.coords.pytpm), 20
 s06 (in module astrolib.coords.pytpm), 20
 setunits() (astrolib.coords.angsep.AngSep method), 14

T

tpmstate() (astrolib.coords.position.Position method), 8

U

utc2jd() (in module astrolib.coords.astrodate), 17

W

within() (astrolib.coords.position.Position method), 9